Navigation tab

Overview

Configure site navigation features such as menus and error redirects.

To Access

From the General Admin page, click the **Navigation** tab.

Option	Description	Default
SmartMenus	Add "SmartMenus" to Bootstrap menus. See smartmenus.org for more.	
Menu user levels	Enables control of the per-group visibility of menu options	
Featured links	A simple menu system to display external web pages in a new browser tab or an iframe within the site, etc.	
Use folder icons for menu section (parent) items	When a menu isn't set as a Bootstrap or CSS menu, use folder icons for menu section items (rather than plus/minus signs).	
Menu icons	Allows icons to be defined for menu entries	
Default path for the icons		
Edit menu icon	Adds an icon on the navbar to edit menu entries	
Jse group homepages	Users can be directed to different pages upon logging in, depending on their default group.	
Go to the group homepage only if logging in from the default homepage		
Use the top page of a Tiki eature as the homepage	Select the Tiki feature to provide the site homepage. Only enabled features are listed.	
Jse custom homepage	Use the top page of a Tiki feature or another homepage This option will override the Use Tiki feature as homepage setting.	
Homepage URL		

Related Topics

Navigatio

n

Overview

Menus

Option	Description	Default
Homepage Browser title	Customize Browser title for the custom homepage	
Wiki homepage	The default home page of the wiki when no other page is specified. The page will be created if it does not already exist.	
Home blog (main blog)		
Home forum (main forum)		
Home file gallery (main file gallery)	Select the default file gallery	
Domain prefix handling	Strip or automatically add the "www." prefix on domain names to standardize URLs.	
Domain redirects	When the site is accessed through specific domain names, redirect to an alternate domain preserving the URL. Useful for domain name transitions, like tikiwiki.org to tiki.org.	
	One entry per line, with each entry a comma-separated list: old domain, new domain	
Redirect on error	On an error, refresh to the homepage as specified on the Admin General page.	
Redirect to similar wiki page	If a requested page doesn't exist, redirect to a similarly named page	
On permission denied, display ogin module	If an anonymous visitor attempts to access a page for which permission is not granted, Tiki will automatically display the Log-in module. Alternatively, use the Send to URL field to display a specific page (relative to your Tiki installation) instead.	
Send to URL	URL to redirect to on "permission denied"	
The URL that the anonymous user is redirected to when a page is not found		
JRL the user is redirected to after account validation	The default page a Registered user sees after account validation is "tiki-information.php?msg=Account validated successfully". Default: tiki-information.php?msg=Account validated successfully.	
Alternate registration page	Enter URL of a custom registration page. Tiki will automatically redirect default registration page (tiki-register.php) to this page.	
JRL Suffix Cleaner	When the requested page does not exist, tests removing 1 or 2 of the last characters from the URL to see if it gets an existing page.	

Option	Description	Default
JRL to go to when clicking on a username	URL to go to when clicking on a username. Default: tiki- user_information.php?userId= (Use for login name and No value assigned for userId))	
Sitemap protocol	Allows generating site maps based on the Sitemap protocol, in the form of XML documents. Mostly used to facilitate indexation of a site by web search engines.	
Close site	Use this setting to "close" the Tiki site (such as for maintenance). Users attempting to access the site will see only a log-in form. Only users with specific permission will be allowed to log in. Use the Message to display to specify the message that visitors will see when attempting to access your site.	
<u> Fitle</u>		
Message		
Close site when server load is above the threshold	Use this option to "close" the Tiki site when the server load exceeds a specific threshold. Only users with specific permission will be allowed to log in. Use "Maximum average server load threshold in the last minute" to define the maximum server load. Use the "Message to display" to specify the message that visitors will see when attempting to access the site.	
Maximum average server load threshold in the last minute		
Site Busy Title		
Site Busy Message		
Breadcrumbs	Indicates the navigation path through parent pages to the current page. Unmaintained feature	
Prefix breadcrumbs with 'Location : "	Place the term "Location:" in the breadcrumbs.	
Site location bar		
_arger font		
Jse page description		
Namespace	Enable namespaces feature for wiki pages.	
Namespace separator	Select the character, symbol, or text to use as the namespace separator.	
Hide namespace indicator in structure path	Hide namespace indicator in structure path.	

Description	Default
Useful to avoid conflicts with C++ scope operators or default namespace separator	
The character(s) to use as a delimiter in the page name. The portion of the name after the character(s) will not be displayed. If the page name display stripper conflicts with the namespace separator, the namespace is used and the page name display is not stripped.	
	Useful to avoid conflicts with C++ scope operators or default namespace separator The character(s) to use as a delimiter in the page name. The portion of the name after the character(s) will not be displayed. If the page name display stripper conflicts with the namespace separator, the namespace is used and the page